

# **Reference Manual**

# Version 30.0

**Recommended system: Windows 7-11/64-bit** 

## **DISCLAIMER.**

Bodzio Software makes no warranties, either expressed or implied, with respect to the program described herein, its quality, performance, merchantability, or fitness for any particular purpose. This program is sold "AS IS". The entire risk as to its quality and performance is with the buyer. In no event will Bodzio Software be liable for direct or indirect, incidental or consequential or any other damages resulting from any defect in the program, even if it has been advised of the possibility of such damages.

## CONDITIONS OF USE.

No part of this publication may be reproduced, stored in a retrieval system or transmitted in any other form or by any means, electronic, mechanical, photocopying, or otherwise without prior written permission of Bodzio Software.

## WARRANTY.

Bodzio Software will replace any defective media (CD-ROM) within 28 days of receipt of any faulty media.

Commercial manufacturers of speaker systems should be aware that some design topologies referred to in the SoundEasy manual and program screens may be part of a registered or patented design by another company or individual. Companies who wish to manufacture a product based on the design results of SoundEasy should assure themselves that no copyright or patent is being infringed.

## Contents

Program Overview       1.1         General Program Specification       1.3         Software Functions Performed       1.4         Installation       1.7         The Screens as Processing Tools       1.7         Printing Session Results       1.8         Saving New Driver       1.10         India Data File       1.10         Pict Compatibility       1.10         Preference Screen       1.11         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Driver & Project Notes       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Dart 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Create Library Of Drivers       2.1         Create Library Of Drivers       2.1         Entering BPL and Impedance Curves       2.2         Hand Drawing Data Points on Screen       2.9         Hilbert-Bode Transform Tab       2.10         HBT Guiding Filter       2.13         Entering Irrequency Response       2.9         Hilbert-Bode Transform Tab       2.14 <th>Part 1 - SoundEasy Fundamentals</th> <th></th>	Part 1 - SoundEasy Fundamentals	
General Program Specification       1.3         Software Functions Performed       1.4         Installation       1.7         The Screens as Processing Tools       1.7         Printing Session Results       1.8         Saving New Driver       1.10         Loading Data File       1.10         For Compatibility       1.10         Version Results       1.8         Saving New Driver       1.10         User Interface Customization       1.11         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Cate Library Of Drivers       2.1         Create Library Of Drivers       2.1         Create Library Of Drivers       2.2         Hand Drawing Data Points on Screen       2.2         What To Do If You Only Have SPL Graph       2.3         Entering Frequency Response       2.9         Hilbert-Boode Transform Tab <td< th=""><th>Chapter 1 . Introduction</th><th>1.1</th></td<>	Chapter 1 . Introduction	1.1
Software Functions Performed1.4Installation1.7The Stereens as Processing Tools1.7Printing Session Results1.8Saving New Driver1.10Loading Data File1.10Preference Screen1.10Preference Screen1.11MLS Measurement Screen & Editor Screen1.13Driver & Project Notes1.13Printing Driver & Project Notes1.13Printing Driver & Project Data1.14Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 - Working With SoundEasy ToolsChapter 2. Using SoundEasyChapter 2. Using SoundEasy2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.13Entering Driver's Data2.13Variable Slope Filters2.13Variable Slope Filters2.14Impedance Models2.15Speaker-Microphone Distance2.16Impedance Models2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.12Splicing Measured And Modelled Frequency Responses2.23String Measured To Divers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Meas	Program Overview	1.1
Installation       1.7         The Screens as Processing Tools       1.7         Printing Session Results       1.8         Saving New Driver       1.10         Loading Data File       1.10         File Compatibility       1.10         Preference Screen       1.10         User Interface Customization       1.11         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Create Library Of Drivers         Create Library Of Drivers       2.1         Entering SPL and Impedance Curves       2.2         Hand Drawing Data Points on Screen       2.3         Entering Driver's Data       2.13         Entering Driver's Data       2.13         Variable Slope Filters       2.13         Variable Slope Filters       2.13         Variable Slope Filters       2.14         Impedance Data       2.14         Manually Entering Zin Impedance Data       2.15         Speaker-Microphone Distance       2.16	General Program Specification	1.3
The Screens as Processing Tools       1.7         Printing Sewsion Results       1.8         Saving New Driver       1.10         Loading Data File       1.10         Pile Compatibility       1.10         Preference Screen       1.10         User Interface Customization       1.11         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Create Library Of Drivers       2.1         Create Library Of Drivers       2.1         Create Library Of Drivers       2.2         Hand Drawing Data Points on Screen       2.10         HBT Guiding Filter       2.13         Variable Slope Filters       2.13         Parting Impedance Data       2.14         Impedance Models       2.15         Speaker-Microphone Distance       2.16         Suspension System – Spiders       2.17         Enclosure Dimensions       2.18	Software Functions Performed	
Printing Session Results       1.8         Saving New Driver       1.10         Loading Data File       1.10         File Compatibility       1.00         File Compatibility       1.00         Preference Screen       1.10         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Create Library Of Drivers       2.1         Create Library Of Drivers       2.1         Entering SPL and Impedance Curves       2.2         Hand Drawing Data Points on Screen       2.2         What To Do If You Only Have SPL Graph       2.3         Entering Iripedance Bata       2.10         HBT Cluding Filter       2.13         Variable Slope Filters       2.13         Variable Slope Filters       2.13         Variable Slope Filters       2.14         Manedance Transform Tab       2.16         Suspension System – Spiders       2.1	Installation	1.7
Saving New Driver       1.10         Loading Data File       1.10         File Compatibility       1.10         Preference Screen       1.10         User Interface Customization       1.11         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Create Library Of Drivers       2.1         Create Library Of Drivers       2.1         Create Library Of Drivers       2.2         Hand Drawing Data Points on Screen       2.2         What To Do If You Only Have SPL Graph       2.3         Entering Frequency Response       2.9         Hilbert-Bode Transform Tab       2.10         HBT Guiding Filter       2.13         Variable Slope Filters       2.13         Speaker-Microphone Distance       2.16         Impedance Models       2.17         Speaker-Microphone Distance       2.16         Speaker-Microphone Distance	The Screens as Processing Tools	1.7
Loading Data File1.10File Compatibility1.10Preference Screen1.10User Interface Customization1.11MLS Measurement Screen & Editor Screen1.13Driver & Project Notes1.13Printing Driver & Project Data1.14Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 - Working With SoundEasy ToolsChapter 2. Using SoundEasyC.1Create Library Of DriversC.1Create Library Of DriversC.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL GaphC.13Entering Driver's DataEntering Irequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Variable Slope Filters2.15Impedance Transfor Function2.14Impedance Models2.15Speaker-Microphone Distance2.16Suspension System – Spiders2.17Adding/Subtractin diffraction To Driver Transfer Function2.21Adding/Subtractin diffraction To Driver Transfer Function2.24Adding/Subtractin diffraction To Driver Transfer Function2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.24Loading Project Files2.38<	Printing Session Results	1.8
File Compatibility       1.10         Preference Screen       1.10         User Interface Customization       1.11         MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Chapter 2. Using SoundEasy       2.1         Create Library Of Drivers       2.1         Create Library Of Drivers       2.2         Hand Drawing Data Points on Screen       2.2         What To Do If You Only Have SPL Graph       2.3         Entering Frequency Response       2.9         Hilbert-Bode Transform Tab       2.10         HBT Guiding Filter       2.13         Variable Slope Filters       2.13         Entering Impedance Data       2.14         Impedance Models       2.15         Speaker-Microphone Distance       2.16         Supersion System – Spiders       2.17         Enclosure Dimensions       2.18         Quick Assessment of Drivers	Saving New Driver	1.10
Preference Screen1.10User Interface Customization1.11MLS Measurement Screen & Editor Screen1.13Driver & Project Notes1.13Printing Driver & Project Data1.14Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 - Working With SoundEasy ToolsChapter 2. Using SoundEasyCreate Library Of Drivers2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.10Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Variable Slope Filters2.14Manually Entering Zin Impedance Data2.15Speakare-Microphone Distance2.16Inpedance Models2.15Speaker-Microphone Distance2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Measured And Modelled Frequency Responses2.33Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.33Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.34Re-scaling Drivers Data To Different Frequency	Loading Data File	1.10
User Interface Customization1.11MLS Measurement Screen & Editor Screen1.13Driver & Project Notes1.13Printing Driver & Project Data1.14Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 - Working With SoundEasy ToolsChapter 2. Using SoundEasyC.1Entering SPL and Impedance CurvesC.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL GraphC.3Entering Frequency ResponseEntering Frequency ResponseEntering Impedance DataC.10Hilbert-Bode Transform TabC.13Variable Slope FiltersC.13Variable Slope FiltersC.14Impedance DataClass geaker-Microphone DistanceC.16Input Assessment of DriversC.20Using Enclosure Simulation as Full Transfer FunctionC.21Chapter 3. Importing Data FilesAlt Modelled Frequency RageClassessment of DriversC.23Semi-Inductane ModelClassessment of DriversC.23Semi-Inductane	File Compatibility	1.10
MLS Measurement Screen & Editor Screen       1.13         Driver & Project Notes       1.13         Printing Driver & Project Data       1.14         Driver Characteristics Screen       1.16         Help Files On-Line       1.17         Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Create Library Of Drivers       2.1         Entering SPL and Impedance Curves       2.2         Hand Drawing Data Points on Screen       2.3         Entering Driver's Data       2.5         Entering Driver's Data       2.5         Entering Frequency Response       2.9         Hilbert-Bode Transform Tab       2.10         HBT Guiding Filter       2.13         Variable Slope Filters       2.13         Variable Slope Filters       2.16         Speaker-Microphone Distance       2.16         Impedance Transfer Function       2.14         Manually Entering Zin Impedance Burl       2.20         Using Enclosure Simulation as Full Transfer Function       2.21         Speaker-Microphone Distance       2.16         Impedance Model       2.27         Adding/Subtractin diffraction To Driver Transfer Function	Preference Screen	1.10
Driver & Project Notes1.13Printing Driver & Project Data1.14Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 - Working With SoundEasy ToolsChapter 2. Using SoundEasyC1Create Library Of DriversC1Entering SPL and Impedance Curves2.1Entering SPL and Impedance CurvesEntering Driver's Data2.5Entering Driver's Data2.5Entering Driver's Data2.5Entering Driver's Data2.10HBDet Bode Transform Tab2.10HBTGuiding FilterVariable Slope Filters2.13Variable Slope Filters2.13Entering Impedance Data2.15Speaker-Microphone Distance2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.21SoundEasy Labelling System2.31Loading Project Files2.31Loading Project Files2.34Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.11Direct Data Import3.12Importing The LMS Files3.66Importing The LMS Files3.66 <tr< td=""><td>User Interface Customization</td><td>1.11</td></tr<>	User Interface Customization	1.11
Printing Driver & Project Data1.14Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 · Working With SoundEasy ToolsChapter 2. Using SoundEasyC.1Create Library Of Drivers2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Irequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding System Models2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Inporting Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6<	MLS Measurement Screen & Editor Screen	1.13
Driver Characteristics Screen1.16Help Files On-Line1.17Dongle Serial Number1.18Part 2 - Working With SoundEasy ToolsChapter 2. Using SoundEasyChapter 2. Using SoundEasy2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.3What To Do If You Only Have SPL Graph2.5Entering Driver's Data2.5Entering Driver's Data2.10HBT Guiding Filter2.13Variable Slope Filters2.13Variable Slope Filters2.14Impedance Transfer Function2.14Impedance Transfer Function2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.21Adding/Subtractin diffraction To Driver Transfer Function2.21Semi-Inductane Model2.27Adding System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.11Importing Data Tifles3.11Importing Data The Measurement File3.2Importing The LMS Files3.60Importing The LMS Files3.60Importing The IMP Files3.60Importing The IMP Files3.60Importing The IMP Files3.60 <td>Driver &amp; Project Notes</td> <td>1.13</td>	Driver & Project Notes	1.13
Help Files On-Line1.17Dongle Serial Number1.18Part 2 · Working With SoundEasy ToolsChapter 2. Using SoundEasy2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.11Importing The LMS Files3.6Importing The LMS Files3.6Importing The CLIO Files3.10Importing The CLIO Files </td <td>Printing Driver &amp; Project Data</td> <td>1.14</td>	Printing Driver & Project Data	1.14
Dongle Serial Number       1.18         Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy         Create Library Of Drivers       2.1         Entering SPL and Impedance Curves       2.2         Hand Drawing Data Points on Screen       2.2         What To Do If You Only Have SPL Graph       2.3         Entering Driver's Data       2.5         Entering Frequency Response       2.9         Hilbert-Bode Transform Tab       2.10         HBT Guiding Filter       2.13         Variable Slope Filters       2.13         Variable Slope Filters       2.14         Impedance Transfer Function       2.14         Manually Entering Zin Impedance Data       2.15         Speaker-Microphone Distance       2.16         Input Power and Rg       2.16         Suspension System – Spiders       2.17         Enclosure Dimensions       2.18         Quick Assessment of Drivers       2.20         Using Enclosure Simulation as Full Transfer Function       2.21         Splicing Measured And Modelled Frequency Responses       2.33         Semi-Inductane Model       2.27         Adding/Subtractin diffraction To Driver Transfer Function       2.29         SoundEa	Driver Characteristics Screen	1.16
Part 2 - Working With SoundEasy Tools         Chapter 2. Using SoundEasy       2.1         Create Library Of Drivers       2.1         Entering SPL and Impedance Curves       2.2         Hand Drawing Data Points on Screen       2.2         What To Do If You Only Have SPL Graph       2.3         Entering Driver's Data       2.5         Entering Trequency Response       2.9         Hilbert-Bode Transform Tab       2.10         HBT Guiding Filter       2.13         Variable Slope Filters       2.13         Entering Impedance Data       2.14         Impedance Models       2.15         Speaker-Microphone Distance       2.16         Input Power and Rg       2.10         Using Enclosure Simulation as Full Transfer Function       2.21         Splicing Measured And Modelled Frequency Responses       2.23         Semi-Inductane Model       2.27         Adding/Subtractin diffraction To Driver Transfer Function       2.29         SoundEasy Labelling System       2.31         Loading Project Files       2.33         Seri-Inductane Model       2.27         Adding/Subtractin diffraction To Driver Transfer Function       2.29         SoundEasy Labelling System       2.31	Help Files On-Line	1.17
Chapter 2. Using SoundEasy2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System - Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.38Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing The LMS Files3.6Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Dongle Serial Number	1.18
Chapter 2. Using SoundEasy2.1Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System - Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.38Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing The LMS Files3.6Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Create Library Of Drivers2.1Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Speaker-Microphone Distance2.31Dationg Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing The LMS Files3.6Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Part 2 - Working With SoundEasy Tools	
Entering SPL and Impedance Curves2.2Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Speaker-Microphone Distance2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Adding/Subtractin diffraction To Driver Transfer Function2.21SoundEasy Labelling System2.31Loading Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Chapter 2. Using SoundEasy	2.1
Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.9Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Create Library Of Drivers	2.1
Hand Drawing Data Points on Screen2.2What To Do If You Only Have SPL Graph2.3Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.9Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Entering SPL and Impedance Curves	2.2
Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.16Syeaker-Microphone Distance2.16Input Power and Rg2.16Suspension System - Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.33Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.6Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		2.2
Entering Driver's Data2.5Entering Frequency Response2.9Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.16Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System - Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.33Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.6Importing The CLIO Files3.10Importing The CLIO Files3.10Importing The Small/Theile CLIO Files3.10	What To Do If You Only Have SPL Graph	2.3
Hilbert-Bode Transform Tab2.10HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.9Importing The LMS Files3.9Importing The LMS Files3.10Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		2.5
HBT Guiding Filter2.13Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Importing The LMS Files3.6Importing The LMS Files3.9Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	•	2.9
Variable Slope Filters2.13Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Hilbert-Bode Transform Tab	2.10
Entering Impedance Data2.14Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	HBT Guiding Filter	2.13
Impedance Transfer Function2.14Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Variable Slope Filters	2.13
Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Entering Impedance Data	2.14
Manually Entering Zin Impedance Data2.15Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Impedance Transfer Function	2.14
Impedance Models2.15Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	•	2.15
Speaker-Microphone Distance2.16Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The IMP Files3.10Importing The Small/Thiele CLIO Files3.10		2.15
Input Power and Rg2.16Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The IMP Files3.10Importing The Small/Thiele CLIO Files3.10		2.16
Suspension System – Spiders2.17Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	· ·	2.16
Enclosure Dimensions2.18Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		2.17
Quick Assessment of Drivers2.20Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data FilesDirect Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.4Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		2.18
Using Enclosure Simulation as Full Transfer Function2.21Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.4Importing The LMS Files3.9Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Splicing Measured And Modelled Frequency Responses2.23Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The IMP Files3.9Importing The Small/Thiele CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		2.21
Semi-Inductane Model2.27Adding/Subtractin diffraction To Driver Transfer Function2.29SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data FilesDirect Data Import3.1Importing SPL Data from Measurement File3.2Importing The LMS Files3.6Importing The LMS Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	e	2.23
SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The LMS Files3.9Importing The Small/Thiele CLIO Files3.10		
SoundEasy Labelling System2.31Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The LMS Files3.9Importing The Small/Thiele CLIO Files3.10		
Loading Project Files2.38Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The Small/Thiele CLIO Files3.10		
Frequency Range of the Data Stored in Driver And Project Files2.43Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The Small/Thiele CLIO Files3.10		
Re-scaling Drivers Data To Different Frequency Range2.47Chapter 3. Importing Data Files3.1Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Direct Data Import3.1Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10	Chapter 3. Importing Data Files	3.1
Importing SPL Data from Measurement File3.2Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Importing Data With Hilbert-Bode Transform3.4Importing The LMS Files3.6Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Importing The LMS Files3.6Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Importing The IMP Files3.9Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Importing The CLIO Files3.10Importing The Small/Thiele CLIO Files3.10		
Importing The Small/Thiele CLIO Files 3.10		
Importing Data from <b>DAAS 32</b> System 3.11	Importing Data from <b>DAAS 32</b> System	3.11

Exporting SPL/Impedance data files	3.12
Exporting Data	3.13
Importing SPL Files as Polar Plots Data	3.14
Exporting ANSI-CTA-2034 Directivity Data	3.19
Importing ANSI-CTA-2034 Directivity Data from TXT file	3.21
Chapter 4. Enclosure Design Screen	4.1
Background	4.1
Plotting TABs	4.2
Attaching Cursor To Curves	4.2
Enclosure Modelling/Review	4.4
Isobarik Extension	4.7
Vent Calculator	4.7
Enclosure Shapes	4.8
Multiple drivers	4.9
Adjusting Vertical Scales	4.9
Active equalisation	4.10
File Selection for Enclosure Equalization	4.12
Front Baffle Design and Diffraction Distortion	4.13
Diffraction Distortion	4.13
Mutual Radiation Impedance	4.16 4.17
Signal Summation Strategies	4.17
Combining All the Above Operation of the Diffraction Distortion Dialogue Box	4.18
Room Gain Effect	4.20
Passive Radiator Systems	4.28
Tuning The PR	4.28
Transmission Line Systems	4.30
Horn Loudspeakers	4.32
Voice Coil Inductance	4.34
U-Dipole Enclosure	4.35
H-Dipole Enclosure	4.36
Getting More Out of Dipole Plots	4.36
Polar Plots Vertical Offsets for Dipoles	4.37
Le ON/OFF Switch	4.38
Equalizer TAB	4.38
Imperial Units Display	4.39
Enclosure Design Curve Labelling	4.40
Large-Signal Analysis	4.42
Thermal analysis	4.42
How to Determine Thermal Resistances ?	4.43
Port Nonlinearities and Compression	4.45
BL(x) and Cas(x) Analysis	4.53
BL(x) and Cas(x) Dialogue Box	4.60
Harmonic Distortion	4.61
Measuring BL(x) Curve	4.63
Mechanical Model and Volterra Model	4.64
Differential Equations (DE) Model of Loudspeaker	4.65
Enclosure Self resonance	4.66
Enclosure Modes in FEM Brick-Element Model	4.68
Port resonance and Enclosure Modes	4.72
Enclosure Modes in FEM Wedge-Element Model	4.74
Chapter 5. Enclosure optimization	5.1
Background	5.1
Optimization Strategy	5.1
Enclosure Optimization	5.2
Chapter 6. Enclosure Response To Rectangular Function	6.1
Background	6.1

How It Is Done	6.1
Transient Analysis	6.2
Modal Influence on Loudspeaker in Time Domain	6.4
Chapter 7. Car Acoustics	7.1
Background	7.1
The Analysis	7.2
Operation of the 3D Car Audio Screen	7.5

## Part 3 - Working With Crossover Screens

Chapter 8. Using CAD System	8.1
Background	8.1
Pick-and-Place Component	8.1
Connecting Components	8.2
Entering Component Values	8.6
Correcting Simple Errors	8.6
Reversed OPAMPS in CAD	8.7
CAD Editing Functions	8.8
Draw Function	8.8
Erase Function	8.9
Overlap Function	8.9
Undo / Redo Functions	8.9
Wipe Function	8.10
Wipe Wire Function	8.10
Move Function	8.11
Add Function	8.12
Cut Function	8.15
Cut To Hard Disk Function	8.16
Copy Function	8.16
Copy To Hard Disk Function	8.17
Paste Function	8.18
Paste From Hard Disk Function	8.19
CAD Nodes Function	8.19
Schematic Nodes Function	8.20
Modelling Network Behaviour	8.20
Node Arithmetic	8.20
Automatic Node Numbering	8.22
Nodes Tab	8.23
Frequency Tab	8.23
Curve Compare Function	8.25
Time Tab	8.27
Targets Tab	8.28
What is Compensation ?	8.28
Using The Calculators	8.28
Lattice Networks	8.30
Additional Operations	8.32
Crossover Tools Menu Options	8.32
"Preview" Built-in Circuit Window	8.32
Fast CAD Component Tweaking	8.33
Frequency Domain ZOOM	8.34
Linear Frequency Scale	8.35
Multiplot	8.36
Save / Load Circuit	8.38
Tweaking Components – Four Methods	8.38
List Box and Slider	8.38
List Box and Cursor keys	8.40
List Box and Cursor keys and Mouse Wheel	8.41
Direct Component Selection from Schematic	8.41
Grouping Passive CAD components	8.42

Power Dissipation Screen	8.46
Jumping Between Screens	8.47
Recalling Direct Measurements To Compare With CAD simulation	8.48
Mounting Coordinates sIn The System	8.49
High Order Filters	8.50
Shorted And Opened Component	8.51
CAD Plotting Options	8.53
Chapter 9. Filter and Crossover Design	9.0
Background	9.1
Channel Filters or Crossovers	9.1
Using Built-in Filters	9.1
Using Built-in Crossovers	9.4
Active Crossover	9.4
Operational Amplifier	9.5
Network Example	9.6
First Cut Design	9.9
Working With Project Files	9.10
Compensation of Diffraction Distortion	9.13
Passive Time Delay Circuits	9.15
Multi-Way Transient Perfect Crossovers	9.16
Digital Filter	9.20
Operation of the Digital Filter Dialogue Box	9.20
Digital Equalizer	9.24
The Issue of Tails	9.24
Recommended Use of the Equalizer	9.23
Redirecting Outputs	9.27
Time Delayed Filters	9.29
Driver Delayed Offset Using Digital Filter	9.34
Super-Component	9.36
Mega-Components	9.30
Linear Phase Filters	9.39
Modular Crossover	9.41
Using The DCX2496 Digital Crossover	9.45
Bi-Quad Filters	9.49
Linkwitz / Butterworth Asymmetrical Filters	9.52
Linkwitz-Riley Transformer	9.52
Time Delay Circuit	9.53
Notched Crossover / Filter	9.55
Partitioned Convolution	9.56
Generating Filter Impulse Response	9.57
Processing Input Data – Ring Buffer	9.59
Actual Convolution Process	9.59
Partitioned Convolution and Linear Phase Filters	9.61
Second Order Yamanaka Crossover	9.66
Fourth Order Delund Crossover	9.66
Chapter 10. Filter Optimization	10.1
Background	10.1
Optimization	10.1
Selecting Optimization Range	10.3
Additional Shape Control	10.5
Adding Ripples	10.7
Locking Components	10.7
Filter Optimization Example	10.7
Targets Tab	10.12
Optimizer Tab	10.13
Constrained Optimization	10.13
User Defined Target Curves	10.14
Conjugate Impedance Optimizer	10.17

User Defined Simple Target Curves Crossover Design and Optimization Using Off-Axis Curves	10.18 10.19
Chapter 11. Crossover in Time Domain Background Time Response Menu Standard Mode vs. Extended Frequency Mode Nodal Method - How It Is Done ? Adding Several Time Responses Concept Of Fill-In Driver	<b>11.1</b> 11.1 11.1 11.2 11.4 11.6 11.6
Part 4 - Working With System Screens	
Chapter 12. System Response Module Putting It All Together Main "Front Panel" Screen Correlating Display on Different System Screens Comparing driver rotation with microphone rotations Off-Axis Response System Vertical and Horizontal Response Plots Horizontal Dispertion Plots Off-axis SPL for all drivers in the Project File Normalizing Off-Axis Display Using Off-Axis Modelled Responses Working With Project Files Phantom Project Files Phantom Project Files Working With Several Projects System Relative AC Offsets 3D Zoom In Feature 3D Rotation Screen – Z- offset System Time Domain Plots Polar Response & Directivity Index Ribbon And Planar Drivers Icons Automated Generation Of Horizontal And Vertical Polar Plots Polar Plots Representations Baloon Polar Plots	$\begin{array}{c} \textbf{12.1} \\ \textbf{12.1} \\ \textbf{12.1} \\ \textbf{12.4} \\ \textbf{12.6} \\ \textbf{12.7} \\ \textbf{12.8} \\ \textbf{12.10} \\ \textbf{12.12} \\ \textbf{12.13} \\ \textbf{12.13} \\ \textbf{12.13} \\ \textbf{12.15} \\ \textbf{12.16} \\ \textbf{12.16} \\ \textbf{12.16} \\ \textbf{12.17} \\ \textbf{12.18} \\ \textbf{12.19} \\ \textbf{12.20} \\ \textbf{12.21} \\ \textbf{12.22} \\ \textbf{12.25} \\ \textbf{12.26} \\ \textbf{12.28} \\ \textbf{12.31} \\ \textbf{12.37} \end{array}$
Chapter 13. System Optimization Background System Optimization Control Tab Optimization Tab Setting-up For System Optimization Estimating the Required "Attenuation" Parameter and the Frequency Range Deciding Which Components to Optimize Optimization Results Final Comments On Optimization Optimization Algorithm Pre-Distorted/Tilted Frequency Response Adding Ripples Constrained System Optimization Component Type Selection Phase Constrained Optimization Zin Impedance Constrained Optimization Nominating Components From Schematic User Defined Simple Target Curves	<b>13.1</b> 13.1         13.2         13.2         13.2         13.2         13.4         13.5         13.6         13.8         13.9         13.10         13.11         13.12         13.12         13.15         13.16

Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Chapter 14. Enclosure Placement	14.1
Image Method14.2Using the Room Modes Screen14.4Room Acoustics Background14.5Mid-Frequencies Problem14.5Adding More Rays14.6Room Modes14.8Chapter 15. Finite Element MethodThe FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.10Source at Room Nodal Line15.12Vibration Basics15.14Eigenvalue Analysis15.15Jacobian of the Transformation15.16Gaussian Intergration15.17Assembly of System Matrixes15.17Generating Mesh15.17Outrol Dialog Boxes15.19Delaunay Mesh TAB15.10Control Dialog Boxes15.19Delaunay Mesh TAB15.20Some Aspects of Subwoofer Placement15.22Absorption Coefficient15.22Absorption Coefficient15.22Absorption Coefficient15.23Modelling Real Sub-Woofer Placed in Room15.30Modelling Real Sub-Woofer Placed in Room15.30Modelling Real Sub-Woofer Placed in Room15.30	Background	14.1
Using the Room Modes Screen14.4Room Acoustics Background14.5Mid-Frequencies Problem14.5Adding More Rays14.6Room Modes14.8Chapter 15. Finite Element MethodThe FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.12Wethod of Analysis15.12Vibration Basics15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Generating Mesh15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Some Aspects of Subwoofer Placement15.22Absorption Coefficient15.22Absorption Coefficient at the Node15.22Absorption Coefficient at the Node15.22Absorption Coefficient at the Node15.23Modelling Real Sub-Woofer Placed in Room15.30Modelling Real Sub-Woofer Placed in Room15.30	Enclosure Placement	14.1
Room Acoustics Background14.5Mid-Frequencies Problem14.5Adding More Rays14.6Room Modes14.8Chapter 15. Finite Element Method15.1The FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.103D Delaunay FEM Screen15.12Vibration Basics15.14Frequency Response Analysis15.14Eigenvalue Analysis15.14Frequency Response Analysis15.17Nutrodo of Analysis15.12Vibration Basics15.14Frequency Response Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.17Solution of Eigenvalue Problem15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.22Anything In-Between - Modal Equalization15.22Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.20Modeling Real Sub-Woofer Placed in Room15.30	Image Method	14.2
Mid-Frequencies Problem14.5Adding More Rays14.6Room Modes14.8Chapter 15. Finite Element Method15.1The FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.103D Delaunay FEM Screen15.12Wethod of Analysis15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Gaussian Integration15.17Assembly of System Matrixes15.17Jacobian of the Transformation15.17Generating Mesh15.17Outrol Dialog Boxes15.19Delaunay Modes TAB15.20Delaunay Modes TAB15.17Delaunay Modes TAB15.17Delaunay Modes TAB15.10Control Dialog Boxes15.19Delaunay Modes TAB15.20Delaunay Modes TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.28Average Absorption Coefficient at Room15.30Modelling Real Sub-Woofer Placed in Room15.30	Using the Room Modes Screen	14.4
Adding More Rays14.6Room Modes14.8Chapter 15. Finite Element Method15.1The FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Wethod of Analysis15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.17Assembly of System Matrixes15.17Oution of Eigenvalue Problem15.17Delaunay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Aspects of Subwoofer Placement15.22Anything In-Between - Modal Equalization15.22Absorption Coefficient15.23Average Absorption Coefficient15.20Modelling Real Sub-Woofer Placed in Room15.30Modelling Real Sub-Woofer Placed in Room15.30	Room Acoustics Background	14.5
Room Modes14.8Chapter 15. Finite Element Method15.1The FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Frequency Response Analysis15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Some Aspects of Subwoofer Placement15.20Some Aspects of Subwoofer Placement15.22Absorption Coefficient15.32Absorption Coefficient15.33Modelling Real Sub-Woofer Placed in Room15.30Modelling Real Sub-Woofer Placed in Room15.30	Mid-Frequencies Problem	14.5
Chapter 15. Finite Element Method15.1The FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Wibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Frequency response TAB15.20Aspects of Subwoofer Placement15.22Absorption Coefficient at the Node15.27Absorption Coefficient at the Node15.27Absorption Coefficient the Node15.27Absorption Coefficient at In Source15.30Modelling Real Sub-Woofer Placed in Room15.30	Adding More Rays	14.6
The FEM15.1Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Wibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Frequency Response Analysis15.14Gaussian Integration15.17Jacobian of the Transformation15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Mesh TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Room Modes	14.8
Analysing FEM Output15.1Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Wethod of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Staffness and Inertia Matrixes15.15Jacobian of the Transformation15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30Modelling Real Sub-Woofer Placed in Room15.30	Chapter 15. Finite Element Method	15.1
Mesh Tab15.3Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Solution of Eigenvalue Problem15.17Solution of Eigenvalue Problem15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	The FEM	15.1
Modes Tab15.4SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Solution of Eigenvalue Problem15.17Solution of Eigenvalue Problem15.17Delaunay Mesh15.19Delaunay Modes TAB15.20Delaunay Modes TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption15.23Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Analysing FEM Output	15.1
SPL @ Fo Tab15.4Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.22Absorption15.23Absorption15.24Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Mesh Tab	15.3
Frequency Response Tab15.4Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Solution of Eigenvalue Problem15.17Generating Mesh15.19Control Dialog Boxes15.19Delaunay Mesh TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.23Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Modes Tab	15.4
Listening Room Example15.7Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.23Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	SPL @ Fo Tab	15.4
Introducing a Source of Sound15.10Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.22Absorption15.23Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Frequency Response Tab	15.4
Source at Room Nodal Line15.103D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.20Pelaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Listening Room Example	15.7
3D Delaunay FEM Screen15.12Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Introducing a Source of Sound	15.10
Method of Analysis15.12Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Source at Room Nodal Line	15.10
Vibration Basics15.14Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	3D Delaunay FEM Screen	15.12
Eigenvalue Analysis15.14Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.25Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Method of Analysis	15.12
Frequency Response Analysis15.14Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Vibration Basics	15.14
Stiffness and Inertia Matrixes15.15Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.22Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Eigenvalue Analysis	15.14
Jacobian of the Transformation15.16Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.22Some Aspects of Subwoofer Placement15.22Anything In-Between – Modal Equalization15.27Absorption Coefficient at the Node15.27Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Frequency Response Analysis	15.14
Gaussian Integration15.17Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Stiffness and Inertia Matrixes	15.15
Assembly of System Matrixes15.17Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.22Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Jacobian of the Transformation	15.16
Solution of Eigenvalue Problem15.17Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Gaussian Integration	15.17
Generating Mesh15.17Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Assembly of System Matrixes	15.17
Delaynay Triangulation Algorithm15.18Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Solution of Eigenvalue Problem	15.17
Control Dialog Boxes15.19Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Generating Mesh	15.17
Delaunay Mesh TAB15.20Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Delaynay Triangulation Algorithm	15.18
Delaunay Modes TAB15.20Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Control Dialog Boxes	15.19
Frequency response TAB15.20Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Delaunay Mesh TAB	15.20
Some Aspects of Subwoofer Placement15.22Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Delaunay Modes TAB	15.20
Eliminating Mode Using Multiple Subwoofers15.22Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Frequency response TAB	15.20
Anything In-Between – Modal Equalization15.25Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Some Aspects of Subwoofer Placement	15.22
Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30	Eliminating Mode Using Multiple Subwoofers	15.22
Absorption Coefficient at the Node15.27Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30		15.25
Absorption15.28Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30		15.27
Average Absorption Coefficient15.30Modelling Real Sub-Woofer Placed in Room15.30		15.28
Modelling Real Sub-Woofer Placed in Room 15.30		15.30
•		15.30
		15.30

## Part 5 – Easy Lab Advanced – Complete Measurement System

Chapter 16. Linear Analog And Digital Measurements	16.1
Short Review of the Measurement Methods for SPL/Phase	16.1
Anechoic Chamber Type Measurements	16.1
Ground Plane Type Measurements	16.1
Half-Space (Pit) Measurements	16.2
Near Field Measurements	16.2
Maximum-length Sequences	16.2
Basic MLS/FFT specification	16.3
True Frequency Resolution	16.3
Noise In Presentation of MLS Measurement Results	16.4
Additional Hardware Needed	16.4

	164
Operation of the MLS (Digital) Screen	16.4
Measurement Method for SPL	16.5
Measurement Method for Impedance	16.9
MLS Measurement Screen Utilities – Post-Processing	16.12
MLS Measurement System Curve Arithmetic	16.12
Curve Arithmetic Group	16.16
HBT Group	16.16
Microphone Calibration File	16.17
Exporting Data	16.18
Spectrum Analyzer/Signal Generator	16.19
Test Waveform Generator Controls	16.20
Spectrum Analyser controls	16.21
Dual Channels Oscilloscope/Signal Generator	16.21
Test Waveform Generator Controls	16.21
Oscilloscope Screen Controls	16.23
Cumulative Spectral Decay (Waterfalls)	16.25
T/S (Thiele/Small) Parameters Extraction	16.28
Added Mass method	16.30
Delta Vas method	16.31
Extracting Voice Coil Parameters	16.32
Measurement Method for T/S Parameters Extraction	16.33
Advanced MLS And Measurement Features	16.36
Improving Accuracy of T/S Parameters Extraction	16.36
Extracting Enclosure QbParameter	16.37
Zoom-In And Scroll Impulse	16.38
Pre-Emphasized MLS Signal	16.39
Using Input Impulse Buffer	16.40
Impulse Smoothing	16.40
Step Response	16.41
Turning Off Microphone Calibration File	16.42
Adjusting Vertical Impedance Scale	16.43
Measuring R,L,C Components	16.43
Single MLS Channel Mode	16.47
Auto Mode	16.47
Cyclic Mode	16.48
Export Impulse Response	16.48
Delay Read MLS Measurement Mode	16.49
Frequency Warped FFT	16.50
FFT Windows	16.50
Frequency Warping Technique	16.51
Warped FFT Controls	16.53
Attaching Cursor To SPL Curves in MLS System	16.54
MLS Measurements TAB Screen	16.55
Spectrograms	16.56
Setting up CSD Plots	16.61
MLS Calibration Files	16.62
Import of Impulse Response as TXT File	16.64
Symmetrical FFT windows	16.66
Extra-Linear Phase Filtering	16.67
Showing Differential Phase	16.68
Pulse and Bipolar Pulse in Oscilloscope	16.70
Exponential Sine Sweep – ESS	16.70
Reference Channel Processing	16.71
	16.71
Signal Channel Processing	
Comparison between MLS and ESS measurements	16.73 16.74
Loop Test of ESS System Use of Small Front Window	16.74 16.75
	16.75 16.77
SPL Level Display Of the Merged Curves	16.77
Calculator For Vent/Cone SPL Ratio	16.78 16.78
Calibrating Long Lead Resistance Out	16.78

RT60	16.79
Noise in RT60 Measurements	16.80
Making RT60 Measurements	16.81
Description of the RT60 TAB Controls	16.84
THD and IMD System	16.85
Harmonic Distortion	16.86
Intermodulation Distortion	16.88
FM Modulated Signals	16.90
THD System Controls	16.91
Steady-State THD	16.92
IMD Sweep	16.92
THD Sweep	16.93
Cepstral Deconvolution	16.94
Introduction	16.94
Cepstral Deconvolution Algorithm	16.94
Example of Cepstral Analysis	16.96
Learning About Cepstrum	16.103
Example of Woofer Driver	16.106
Final Comments	16.113
Calculator TAB	16.113
Matching Filter Technique	16.115
Matching Filter Controls	16.119
The Wavelet Transform	16.120
Mother Wavelet Self Tests	16.122
Rotating Wavelet Display	16.123
Adjusting "Scale" Variable	16.124
Dissemination of Impulse Response	16.124
Usage With Minimum-Phase Systems	16.127
Usage With Linear-Phase Systems	16.128
Graphical Improvement to CSD plots	16.130
Sliced CSD	16.131
Adaptive Windowing	16.132
Control Dialogue	16.133
Comparison with standard measurements	16.134
MLS SPL Calibration using sine-wave	16.136
Measurement System Set-Up	16.138
Proposed Calibration Sequence	16.143
Complex Smoothing in MLS System	16.149
Direct Measurements Compared With CAD Simulations	16.150
Non-Coherence Distortion	16.152
Calibration	16.154
Loudspeaker Tests	16.157
Minimum-Phase Development	16.158
Woofer Example	16.158
Midrange Driver Example	16.163
Tweeter Example – Sampling 48kHz	16.163
Tweeter Example – Sampling 96kHz	16.167
Input Impedance At High Power	16.170
Semi-Inductance Model	16.171
CSD Comparisons	16.174
Inverse Hilbert-Bode Transform	16.177
Introduction and remainder on HBT	16.177
Introduction to "Phase Slopes" Corresponding to SPL Slopes	16.177
SPL from Phase for Simple Filters	16.177
SPL from Phase for Measured Example Loudspeaker	16.178
SPL from HBT Phase	16.181
SPL sensitivity to attached phase slopes	16.181
SPL Sensitivity to Non-minimum-phase Phase Response	16.182
Conclusions	16.184

Peak Power Dissipation Ratio	16.185
Subtracting diffraction from SPL	16.188
Saving MLS settings to Hard Disk	16.188
Automated Extraction of Minimum-Phase Phase Response	16.190
Tweeter Driver Example	16.191
12" Woofer Driver in Vented Box	16.196
Summary	16.202
Loudspeaker Driver Characterization	16.204
Conclusions	16.209
Automated ANSI-CTA-2034 Measurements	16.210
MLS Measurement TAB	16.211
RS232 Control	16.212
Manual Table Control	16.213
Fully Automated Turntable Measurements	16.216
Cleaning Up Bass Response	16.217
ANSI-CTA-2034 Measurement Set-Up	16.219
ANSI-CTA-2034 Performance Windows	16.221
ANSI-CTA-2034 In CAD and System Design	16.222
Collecting And Displaying ANSI-CTA-2034 Test Results	16.223
The Turntable	16.226
Preliminary Testing of Measured Phase Data Accuracy	16.227
What Can Be Done	16.228
Harmonic Distortion Extracted with ESS Sweep	16.231
Automated Methods For Minimum-Phase Extraction	16.235
Constraint In Automated IHBT Method	16.247
Chapter 17. Analogue Non-Linear Measurements And Modeling	17.1
Non-linear Parameters Estimation using Volterra Series Expansion	17.1
Comments On Performing The Measurements	17.1
Making The Measurements	17.2
Non-linear Parameters Estimation Using Differential Equations Method	17.4
Capture Issues To Consider	17.9
Measurement Method	17.13
Modelling Second Order Systems	17.16
Chapter 18. Recommended Design Sequence – typical workflow	18.1
Single Driver Design	18.1
Multi-Way Sustem	18.7
More Advanced Approach	18.10
EasyLab - Advanced. Versatile and Powerful	18.13
Recommended Reading	18.15
Software Security	18.17
USB Dongle	18.17
Missing Components From Control Boxes	18.23
Sound Card Selection	18.24
Motherboard Audio Codec Issues	18.25
Chapter 19. DSP Tools	
System Phase Linearizer	19.1
Other Controls	19.1
Synthesized Bass	19.3
Alittle Digression into Music	19.4
Somewhat Different Approach	19.4
Bass Synthesizer	19.5
How Does It Actually Sound	19.7
Conclusions	19.8
Advanced System Phase Linearizer	19.9
Real-life Loudspeaker Example	19.9
On-axis Vs. Off-axis Equalization	19.11

Amplitude Equalizer Design	19.12
Inverting System Phase	19.14
Conclusions	19.15
Description Of Controls	19.16
Digital Room Equalizer	19.17
Practical Tips on Room Equalization	19.18
Description of the DRE Process	19.19
Making Averaged SPL Measurements	19.19
Removing Troughs / Dips	19.21
Selecting HBT Parameters	19.22
DRE Controls	19.24

#### Part 1

#### **SoundEasy Fundamentals**

### **Chapter 1. Introduction**

The theory of the electrodynamic loudspeakers has advanced a great deal over the last four decades. Because of the popularity of multi-driver speaker systems (and their attendant design difficulties) this subject has been the focus of engineering and academic research. As a result, the advantages and limitations of the multidriver speaker systems (and the various crossover types) have been exhaustively debated and published. Loudspeaker manufacturers, recognising these scientific advances, now provide their products with rather detailed driver specifications. Mathematical models which approximate real drivers and the various types of enclosures have been developed and confirmed in practical applications. SoundEasy computer program was developed to consolidate the accumulated knowledge. The resulting computer simulation deals with low, mid and high frequency electrodynamic drivers mounted in a suitable enclosures (one which provides optimum loading for the drivers across the required frequency range). Individual drivers may need to be compensated in time and frequency domains and the selected units eventually mounted in an enclosure to operate as a system. SoundEasy offers the designer a set of powerful tools, covering all aspects of system design in one convenient package. Advances in Computational Acoustics enabled us to implement powerful Finite Element Method for the purpose of evaluating room acoustics. We have incorporated two measurement techniques; analog and digital to assist you with data acquisition. SoundEasy is aimed at more advanced range of users, but beginners will be surprised how easy it is to evaluate drivers, enclosures and crossovers and produce a working speaker system from them. Professional designers and advanced hobbyists will benefit from the ability to explore the various alternative designs and as a result be able to more quickly choose and optimize both the enclosures and crossovers.

This software release reflects our continual effort to provide you, the User, with a friendly tool and a lot of enjoyment during your design/experimentation effort and is recommended as an upgrade for all **SoundEasy** users.

#### **Program Overview**

SoundEasy V30 is our latest release of the Windows7/11 64-bit version of the program. List of Version 30 enhancements over Version 29 is shown below:

- 1. Two automated methods for extracting minimum-phase response from measurements. This is major feature in SoundEasy, and represents the most comprehensive set of tools to extract the minimum-phase response.
- 2. Matching Filter functionality returns back to the V25/26 version with improvements.
- 3. Increase search window in Zin measurements 100000bins.
- 4. Fixed bug in Turntable section when loading IR.
- 5. Diffraction Bevel and Round options plotting bug fixed.
- 6. Switchable labels in crossover CAD window.
- 7. Significant speed improvements (5x-10x) in Variable Windows MLS measurement section due to new algorithm.
- 8. Added Vertical Angle indicator when plotting V-Polar diffraction curves.
- 9. Updated User Manual.

SoundEasy is a menu driven software, which requires Windows (TM) to be installed on your computer. The program takes advantage of the SVGA graphics capabilities of your computer (min. screen size is 1940x1080 pixels) and enables you, the designer, to create, evaluate and then optimize 2, 3, 4 or 5 way loudspeaker systems **prior** to starting the assembly of the enclosure. Most errors or problems can be intercepted and corrected at a very early stage of the design, without cost penalties! Greater speed and design accuracy can be achieved when designing the enclosure, filters, and complete crossover.

A **Hilbert-Bode Transform** technique is employed which re-creates complex transfer function from the frequency response of a driver. Using this method, the magnitude and phase response of a driver across the desired frequency range can be obtained. You can now take into account phase errors introduced by the driver or drivers at the crossover point. The data imported from the measurement system may be in error. One of the **sources of data errors** can be the noise level in your measurement system (sound cards). This problem may manifest itself as amplitude errors and particularly **phase errors at lower signal levels**. SoundEasy allows you to add small time delay to somewhat compensate for the measurement system errors. Comparison of the imported phase with no acoustic delay with the phase generated by the built-in Hilbert-Bode Transform will tell you if your measured data is correct. One of the most significant sources of errors in speaker system design is **the loading of the crossover** by the complex input impedance of the driver. (Crossover design can be a formidable task when "ideal" loads are replaced by "real" drivers).

**Non-Coherence Distortion analysis** is a **dual-channel method of analysis** of non-coherence between the reference signal (stimulus) and the response of the system under test. Interestingly, the NCD method, provides continuous distortion curve versus frequency and can provide single number, as the Total Non-Coherent Distortion figure. Most importantly, the preferred stimulus signal can be noise, music or speech. This is where the NCD method is most useful. **Inverse Hilbert-Bode Transform** (IHBT) requires **asymptotic phase slopes** to be attached to the phase response at selected frequency points. This combined phase response constitutes input data into the IHBT algorithm.

Using the built-in **electronic CAD system**, SoundEasy enables you to model the behavior of the crossover when loaded by the driver in an enclosure and observe the dramatic effect on the frequency response curve of the crossover that the driver may have. A suitable design compensation network can be also created on the same screen and the effect on the crossover re-examined. The program allows you to pin-point problems and test possible solutions so that the frequency response of the crossover is as close to the "ideal" as possible. The effect of the statistical spread (variations within a specific model) of loudspeaker parameters can be quickly evaluated using **parametric family plots**. (This will be of great assistance to loudspeaker manufacturers when setting their quality tolerance levels). In order to provide you with a high degree of flexibility, a **schematic capture** module is provided as one of the SoundEasy tools.

The process supports a 'pick-and-place' technique for creating schematics and is based on **powerful 'Nodal Analysis'** (matrices of complex numbers) techniques, employed by most world-recognized electronic CAD systems. An advanced numerical optimization method called the 'Method of Rotating Coordinates' is used throughout the program to optimize the enclosure parameters, the individual filters and the complete crossover. The Method of Rotating Coordinates was selected for its speed and accuracy. Box, crossover and **system** response to a rectangular pulse can be evaluated in **time domain** and correlated with its frequency response. SoundEasy offers here several tools such as DSP techniques (1024 point FFT & IFFT), Lattice Network Calculator, and Network Analysis in Time using Runge-Kutta methods.

The final consideration (prior to the commencement of listening tests) is usually the question of enclosure positioning within your listening environment. This problem can be very complex if all the influencing factors are considered. SoundEasy offers a solid, engineering approach to improve the overall sound quality of the system in the testing position using **Ray Summation**, Image Summation and most importantly, the accurate FEM methods (see Chapter 15). Current SoundEasy release allows you to actually plot "room contribution" effect vs. frequency for any position of two subwoofers in a non-rectangular room. When a high power is applied to the driver for a prolonged period of time, the voice coil heats-up and the performance of the driver deteriorates. Enclosure Modes are also calculated using the FEM.

The effects of the **voice coil temperature** on the frequency response of the high power drivers can be evaluated at all power levels. Also, the temperature of the magnetic structure can be calculated if the thermal resistances of the driver are known. Detailed analysis can now be performed on all eleven types of enclosures for any power level between 1mW to 1000W. Current version of the program incorporates Large-Signal Analysis based on BL(x) and Cas(x) non-linearities. Both parameters are approximated as a set of curves, which can be edited for the best fit with a known parameters of the driver. A Total Harmonic Distortion (THD) estimator is also built-in. To top it all, port non-linearities are also simulated. A complete off-axis analysis can be performed in the program and horizontal and vertical SPL plots are available. Titling drivers is available and this will come very handy when attempting to design an enclosure with the front baffle of a complex shape.

**Digital Equalizer** provided with the CAD section of the program is capable of "non-minimum phase" equalization of the loudspeaker system, and therefore, correcting amplitude and time domain delays of 5-way loudspeaker system. An extension of this concept is equalization of the "speaker-to-ear" room transfer function – the **Digital Room Equalizer (DRE).** The DRE is a "minimum-phase" equalizer, which in addition, includes a delay function as well. This new feature has been implemented to allow you to "deconvolve" or "equalize" areas of your listening room. The issue of room equalization has been described in many publications, and seven of them are listed below to start your creative thinking process flowing.

SoundEasy also incorporates a measurement system – **EasyLab**. The system has been designed and optimised for analogue and digital loudspeaker and room acoustics measurements. Two measurement systems: **MLS and ESS measurement systems** have been incorporated with **Cepstral Deconvolution and Matching Filter technique. STFT Spectrograms, Wavelet Analysis** are implemented and Non-Coherence Distortion analysis is the latest addition to EasyLab.

ANSI-CTA-2034 automated measurement system, capable of controlling a turntable, is now built-in.

#### **General Program Specifications.**

Environment:	Windows 7/64-bit.
User interface:	Mouse, Keyboard, Windows.
Program control:	Mouse, Menus, Buttons.
Hard copy:	Graphics Printer, e.g.: LaserJet 5L.
Screen output:	1980x1080 pixels min, 256 colours
Processor:	i7-960, 2.8GHz or better is recommended.
RAM	1Gb Mb MINIMUM REQUIRED for SoundEasy.
Hard Disk required:	40.0 Mb min.

#### Short Summary of the Main Software functions performed

#### 1. Loudspeaker driver reference library creation.

The program will accept the electro-mechanical (including acoustical center offset) and frequency response parameters of each driver. These parameters can be saved to disk for later editing. Frequency response is entered as SPL (1 meter, 1 watt) for 750 discrete frequencies, separately selected for woofer, upper base, midrange, tweeter and super tweeter. Complex transfer function of each driver is then re-created by the user. Program facilitates importing frequency response and impedance data and manual editing of the imported files. Two **accurate impedance models** are provided.

#### 2. Loudspeaker enclosure design.

The function is implemented by means of entering vital parameters of the enclosure: volume, Q-factor, tuning frequency or TL line length and so on. The software will then plot the frequency response, relative cone excursion, the system (driver + enclosure) impedance for a specified driver, system phase response and group delay (and more curves in total, depending on the enclosure type).

Sealed, vented, double-chamber and triple-chamber, sealed-vented, vented-vented, passive radiator, transmission line, horn enclosures, vented/TL subwoofers, U-Diploes and H-Dipoles (total of 13 enclosures) are supported (both sealed and vented enclosure design functions are provided for midrange and upper bass drivers). Parametric family curves can be obtained by incrementing (within a predetermined range) one of the enclosure parameters. This automatic process will plot the changes in frequency response, cone excursion and system impedance. Isobaric extension is available for sub-woofer system. 'Multiple drivers' variations are also modeled. **BL(x)**, **Cas(x)**, **temperature and port non-linearity** and compression modeling are included. You can also print **detailed dimensions of a rectangular enclosure** with bracing and all parasitic elements inside the box accounted for.

## 3. Loudspeaker enclosure optimization.

This advanced feature also takes advantage of the "Method of Rotating Coordinates". All three enclosure parameters: Fp, Ob and Vb are optimized at the same time as the program attempts to obtain the "optimally flat" alignment for a given loudspeaker. Sealed, vented and band-pass type 2 enclosures can be optimized for the bass driver, upper bass and the midrange driver. Several reference alignments are provided.

## 4. Compensation of the driver impedance, amplitude peaks or time delays.

- This function enables you to :
- Cancel voice coil inductance
- Compensate for the upper bass/midrange/tweeter/super tweeter resonant impedance peak.
- Reduce amplitude irregularities.
- Adjust sensitivities of the higher frequency drivers.
- Insert a time delay network, such as Lattice Network to offset the acoustic center of the driver.

Driver compensation can result in an improvement in the performance of the crossover. The resulting amplitude/phase/impedance/group delay plots are available for all three drivers. Full examination can allow the designer to model the behavior of the designed network. L-type attenuation pads and the interaction of the woofer and midrange drivers with their enclosures can also be evaluated. Active components (OPAMPS) are provided.

## 5. Crossover filter design.

SoundEasy provides you with a full electronic **CAD GUI for the schematic capture** process. This allows you to design ANY type of circuit or crossover (parallel, series, cascaded and so on...).

There are also several types of circuits and many types of pre-built crossover filters provided: **Bullock**, **Butterworth**, **All-Pass**, **Linkwitz-Riley and Bessel** filters. You can also select four rates of rollover for lowpass, high-pass and band-pass configurations. Amplitude/phase/impedance/group delay plots are available to enable full evaluation of the design. Bullock coefficients for all filter orders are dynamically calculated. As a result, the effect of the crossover on the real driver frequency response can be readily observed. Active filters (OPAMPS) are also provided. The **Add Network function** allows you to quickly put together complex, uneven order crossovers.

The program also includes extensive support for **Transient-Perfect** crossovers and **Digital Equalizer and Filtering** option. The processing power of the CAD system is enhanced by Super-Components and Mega-Components. Finally, **Cut-and-Paste** method combined with the ability to have 3 Projects opened at the same time, allows you to create extremely complex crossover systems. In the concept of Modular Crossover, the filters are defined in terms of cut-off frequencies and slopes. There is also an array of shaping circuitry available. SoundEasy now includes 18 CAD processing functions:

- 1. **Draw** For "pick-and-place" components and drawing connections
- 2. Erase For erasing single connection or component
- 3. **Overlap** Changing components without disconnecting or moving them
- 4. Undo / Redo For "undoing" the last 4 steps, and cancelling the last Undo operation
- 5. **Wipe** For disconnecting and erasing the component
- 6. Wipe Wire For erasing wires
- 7. Move For disconnecting and moving component around
- 8. **Group** For grouping components
- 9. Add For adding a complete, pre-calculated filter or even a complete crossover to your schematic
- 10. **Cut** For cutting a section of the schematic

- 11. Cut To Hard Disk For cutting a section of the schematic and saving it to HD
- 12. Copy For duplicating a section of the schematic
- 13. Copy To Hrd Disk For duplicating a section of the schematic and saving it to HD
- 14. **Paste** For pasting the Cut section
- 15. Paste From Hard Disk For pasting the Cut section from HD.
- 16. Cad Nodes For switching ON/OFF dots (nodes) on CAD area.
- 17. Schematic Nodes For switching ON/OFF node numbering on CAD area.
- 18. In addition, there are over 100 in-built filters and crossovers to choose from.

## 6. Crossover filter optimization.

The optimization process takes into account the driver's complex transfer function, the effect of the enclosure, the input impedance and the compensation network characteristics. As a result of the optimization, alternative low-pass, high-pass or band-pass filter components are calculated. This feature employs the Rotating Coordinates Method and can optimize complete crossover. Target curves can be extensively modified by tilting, stepping, and **adding ripples**.

## 7. System frequency response evaluation.

This feature enables you to plot the combined frequency response of the complete speaker system taking into account all driver, crossover and enclosure related parameters. SPL amplitude plots are provided, together with number of impedance/phase and delay plots. As well phase reversal effects for all drivers can be observed.

## 8. System frequency response optimization.

A number of approaches can be tried using this tool. The filter components of any driver can be optimized over a selected frequency range in order to obtain the flattest possible system response. Alternatively, the target frequency response can be heavily distorted, thanks to the **new "Add Ripples" feature**. Once again, the Method of Rotating Coordinates is used in this tool. Optimization can be performed for SPL, phase and Zin constraints.

## 9. Frequency response of the system "in-room".

The effects of placing the enclosure in the corner of a room on the frequency response can be estimated with this feature. Another screen allows for frequency response evaluation within 10-200Hz in a fully enclosed room of ANY shape.

#### 10. Calculators.

L-pad calculator, Series LRC calculator, Zobel Network calculator, Impedance peak suppressor, Lattice Network Calculator, Vent Calculator, Rectangular Enclosure Details and Enclosure Shapes calculators.

#### 11. Large-Signal analysis.

The program accepts thermal resistances of the driver's voice coil and magnetic structure and enables you to examine all modeling curves and structure temperatures at all input power levels from 1mW to 1000W. Power compression" effect can be clearly observed on the frequency response and all other plots. In addition, **port non-linearities** and non-linearities of the suspension system can be modeled and editing of **BL(x) and Cas(x)** curves is provided. Finally, **Total Harmonic Distortion (THD)** of the driver+enclosure can be estimated over 5Hz-2kHZ frequency range of interest.

## 12. Polar and "Straight Line" vertical and horizontal plots.

**Horizontal, vertical and tilted location** of the drivers on the front baffle can be varied and the interaction of the complete system examined at any frequency. This is particularly important at the crossover points. There are three dialogue boxes the implement calculators and plotting functions for "off-axis" response.

#### 13. Time domain responses.

Enclosure response to a rectangular wave can be observed in time domain. This enables the designer to determine the amount of tolerable "ringing" generated by some specific alignments. This analysis is available for all seven enclosure types. Frequency of the rectangular wave can be adjusted between 1 and 500 Hz and FFT and IFFT techniques are employed. Finally, crossover response to a rectangular function can also be observed in time domain. This useful feature enables you to determine if the crossover is of the "constant voltage" type. This feature operates just like a "digital storage oscilloscope" and allows the designer to add up to 5 curves in time domain. Two methods are implemented: (1) **FFT Technique** and (2) **Modified Nodal Method** in Time Domain.

## 14. Importing data.

SoundEasy allows you to import amplitude/phase and impedance/phase from three measurement systems: (1) IMP, (2) LMS, (3) CLIO, (4) LAUD, (5) MLSSA and (6) DAAS32. Some associated processing functions are also included, so that the imported data can be validated over 10Hz-40kHz frequency range. Small/Thiele parameters can also be imported from CLIO and DAAS32 systems.

## 15. Low-frequency room analysis.

The low-frequency analysis is performed using the FEM method. The FEM is now capable of analysing objects having irregular vertical shape such as arches and pyramids. 2D and 3D FEM screens are implemented.

## 16. Subwoofer design.

Active Equalization function is provided in the "Box" module. You can design the passive/active EQ circuit using "Crossover" module and then use the combined (box+EQ) frequency response optimize the subwoofer design and check it under Large-Signal conditions.

## **17. Enclosure Diffraction Analysis.**

This feature allows the user to mount up to 4 drivers (quad-box) on the front panel and analyze resulting diffraction and mutual impedance effects. Diffraction distortion are best analyzed in an anechoic chamber, where the driver radiates into a full space.

## 18. Implemented Two Small-Signal Measurement Systems.

18.1 Measures SPL and Impedance
18.2 Impulse and Step responses
18.3 Two types of Waterfall analysis
18.4 Small/Thiele parameters
18.5 Enclosure stuffing Qb
18.6 Oscilloscope
18.7 Spectrum Analyser
Requires full duplex, 16/24-bit, stereo sound card.

## 19. Implemented Non-Linear Measurement / Modeller

- 19.1 Volterra Series Expansion Method Measurement System
- 19.2 Non-linear Differential equations Method Measurement System
- 19.3 Non-linear Differential equations Method Modeller

## 20. Implemented RLC Meter

## 21. Room Acoustics – RT60 measurements

## 22. Total Harmonic Distortion and Intermodulation Distortion measurement.

## 23. 6 Advanced DSP functions such as: Digital CAD Filter, Digital CAD Equalizer, Room Equalizer, Bass Synthesizer, Phase Equalisers, Phase/Amplitude Equalizers.

## 25. Cepstral deconvolution and Matching Filter Technique

Assist in removing room reflections from MLS measurements.

The above list is only intended to highlight many of the built-in features of SoundEasy. There is more to be found in the program, while you learn its true potential and flexibility. We suggest, you may want to start with Chapter 18 – which provides you with an overall direction and a "top level" set of hints to manage the program and your design process. Hopefully, you will find the manual informative enough to describe all functions incorporated in the program. We have also strived to provide you with numerous, easy to follow examples, that may provide an additional degree of confidence in your design activities with SoundEasy. Finally, four fully edited data files (3 driver files and one project file) have been provided with the program, so you can start using the program simply by loading any of the files and immediately exploring SoundEasy processing power.

## Installation.

1. SoundEasy is distributed on CD-ROM for Windows7/64 as an executable code, without installation program. Manual installation would simply require you to create a directory, say, "SE" in the ProgramFiles on your C: drive, then copy all files from the CD-ROM and finally create "desktop icon" for the SoundEasy.exe code – as simple as this.

2. When run first time, the program will creat Preferences file, where the information about the size and location of windows and dialogue boxes is stored. You will need to adjust the sizes are your require.

3. For dongle driver installation please see "Dongle\_Driver\_Readme.txt" file.

4. User Manual may be update from time to time by Bodzio Software. For the latest version, please visit <u>www.bodziosoftware.com.au</u>

5. When finished with the software installation, **connect the Security Key - see page 18.8.** SoundEasy ships with the standard Security Key driver for WinXP. For other systems, we have also included a dongle driver installation program that automatically detects your operating system and installs appropriate driver. The program is called "InstDrv.exe". You can run it from your CD-ROM and all you need to do is to follow a couple of simple steps.

6. For the latest Rockey4 drivers please visit <u>http://www.ftsafe.com/download/rockey4.html</u>

## 7. SoundEasy and BoxCad Manuals do not have icons created during installation process. Both manuals reside on the CD-ROM as "Adobe Acrobat PDF" files.

#### **Screens As The Processing Tools**

The operation of SoundEasy resembles a chain of "production line" activities. The raw driver data, entered at the beginning of the design process is being manipulated, processed and expanded by the rest of the modules. Each module operates on the data provided by the previous module. See Fig 1.1 for the path of data flow.





Figure 1.1 Information and data flow within SoundEasy

Data flow is sequential. This process does not allow you to jump a module. For example, you cannot use the summation screen to process data provided by the 'Box' module. The "Crossover" and summation screens requires up to 5 files to be loaded at the same time. To speed up the process, a Project File is being used, where paths and file names can be stored for automatic loading. Passive or active circuits can be created using Crossover Screen and then loaded back into the Box Screen to be included in the modeling of the enclosure frequency response (EQ circuit for subwoofer design). The description of the modules as tools is deliberate. It is essential to the successful use of this program that each module is seen as a tool which the designer uses to work on the available data and arrive at desired results. More exact block diagram of module operation is provided in the following sections of this manual.



In the above example, 'Box' module were used to (1) synthesize driver's input impedance while mounted in the selected box -  $Z_3(s)$  and (2) generate transfer function of the driver mounted in the box - $F_3(s)$ .  $Z_3(s)$  becomes the load impedance for the compensation circuit - that is, if you use loudspeaker symbol in the compensation network developed using 'Crossover' module. Also, total transfer function is now  $F_3(s) * F_2(s)$ . Finally,  $Z_2(s)$  becomes the load impedance for the crossover network, again, if the loudspeaker symbol was used in the crossover network. The total transfer function now equates to  $F_3(s) * F_2(s) * F_1(s)$ . Input impedance of the woofer section is  $Z_1(s)$ ,  $s = j\omega$ .

#### **Printing Session Results**

All images of the program's windows within this manual have been developed using the program's graphics capabilities. Printing session results is achieved by selecting the "Print" option from the window's menu. This selection opens SoundEasy printer dialog box (Fig 1.3) and the user may select orientation of the printout, scaling factor and location of the printout. Some users may give preference to smaller or half-size print-outs. The final dimensions of the print are a combination of the scaling factors entered and the resolution of the printer used. It is therefore recommended to perform a test print-out for the current printer settings and if the results are satisfactory, use the same scaling factor consistently throughout the program. All options selected from the printer dialog box will be saved to the driver's data file. Orientation (Portrait or Landscape) selected from the SoundEasy printer dialogue box must be the same as the one entered in the Standard printer control dialogue box. This is required to avoid graphics being stretched vertically over the whole page by the Standard printer control dialogue box. The "Offset X" and "Offset Y" parameters can be used to move the location of the graph on the printed page independently in X and Y direction. Finally, a small window which appears on the screen and informs the user of the progress of the banded or non-banded print-out.

Printing capabilities of the program were developed for commonly supported printer drivers and tested on number of printers and emulators. If your printer is not operating properly, further customization may be needed, as it is likely, that your printer driver file is supporting only limited functionality or it can not be invoked from within the application program. Also, in case of difficulties, we recommend to experiment with your printer DPI settings and start with low DPI: 75, 150 and then 300. Reduce size of the printout (30%, 50% 80% and 100%) and landscape or portrait orientation.

Please consult Windows<sup>™</sup> manual for screen settings. Low DPI and smaller printout size will work better on lower memory hardware. Finally, please review your printer's manual and make sure, that your printer is set optimally for complex graphics printouts. For example: HP LaserJet 5L with standard 1Mb memory needs to be set to Manual/Raster/300dpi setting for optimum screen dumps. All graphics screens presented in this manual were printed on DeskJet1220C

#### Saving a New Driver

It is recommended that you save intermediate data 3-4 times per design session. To save data select the "Save Driver File" option from the windows menu. **Loading Data File** 

Loading woofer data file is achieved by using the corresponding menu option. Other driver types follow the same procedure. Once the "Open Driver File" option is activated, user may select the whole path, including drive, directory, sub-directories and finally the name of the file. The dialogue box is a standard WinXP<sup>TM</sup> box.

Printout Control 🛛 🔀			
Detected Printer Type: winspool Model: HP DeskJet 1 Port: LPT1:	220C		
Orientation Landscape Portrait Left-Top Corner X Offset: 200 Y Offset: 200	Select Scale 30 % 50 % 80 % Scale: 80 %		
Screen Colors To Capture:			

Figure 1.3 "Print" dialogue box

## **File Compatibility**

SoundEasy V21.00 data files are in a new format. However, files created with versions 18, 19 and 20 can be imported into the program. There are new test files included on the CD-ROM:

- 1. Woofer test files: Test\_21\_W7\_1.wfr and Test\_21\_W7\_2.wfr
- 2. Tweeter test files: Test\_21\_W7\_1.twe and Test\_21\_W7\_2.twe
- 3. Test file for non-linear Method II: Test\_21\_W7\_1\_Non\_Linear.wfr
- 4. Project test files: Test\_21\_W7\_System\_Crossover\_Rotations\_1.hif and Test\_21\_W7\_2.hif

#### **Preferences Screen**

The preference screen is divided into several blocks of common data.

1. Frequency Range.

Before beginning to use the SoundEasy you should decide on what preferences setting you intend to use. SoundEasy is unique in that storage of SPL and impedance data in driver files is associated with specific preference settings for the system and box frequency range. Project files are also associated with a specific system frequency range and any drivers loaded into a project must be associated with the same system frequency range as the project. Additionally, when generating and saving a mic calibration file, the calibration data saved is also associated with the system frequency range. For this reason, it is suggested that when first starting to use SoundEasy you make a decision on what system and box frequency range you wish to use and set these once and then user them for all modeling. Once this decision is made, changing the system or box frequency range can be performed but drivers and system files will not display the correct SPL or impedance data until the frequency range the system frequency range and want to have the SPL and impedance data displayed correctly with this new setting consult main manual regarding exporting and re-importing this data.

Since it would be difficult for the user to remember the correct settings for all saved driver files, when a driver or project file is opened SoundEasy will warn and **based on user selection, will** change the preferences to those in place when a file was saved. In addition to the frequency range preferences there are a number of other preference settings which are less important in that they are not related to how data is saved.

There are three options available: System, FEM and Box. The System option sets the lower and upper frequency limits for all screens with the exception of enclosure design screen. The limits are selected from the provided list boxes and the selected options are saved to driver's data file. We suggest, that you select the most preferred frequency range option and use it consistently within the program. Please pay particular attention to the fact, that importing SPL and Zin data will be arranged depending on the screen frequency range. This has the consequences, that if you import the measurements for one frequency range and then switch the program to another frequency range, the imported SPL/Zin data becomes invalid.

## 2. Colour Scheme.

Several options for choosing colour scheme for plotting curves is also provided. Adjusting colour is as easy as sliding the "Red", "Green" and "Blue" sliders. Pen colours are also editable from the main menu option.

#### 3. Audio Devices.

This section allows you to disable mixer device control by SoundEasy and also invert left and right channels. Also, the **preferred audio devices for input and output can be selected from this screen**.

There are also a check boxes available for setting the whole program to 16-bit or 24-bit sound card operation. Typically, you would make the selection when you install your sound card. It is essential, that you read Chapter 18, pages 18-27 for detailed information related to PC and sound cards.

#### 4. Environment.

There is only one field available for entering the speed of sound you wish to be used for the analogue and digital measurement screens.

## 5. Non-Linear Screen.

There are several list boxes to select the frequency range of the screen, scaling of the THD vertical axis and two check boxes for enabling F4 and F5 display and finally, enabling the THD plots.

All settings of the "Preferences" screen are saved into the preferences file. This file is stored in the same directory as the main executable code and is automatically loaded when the SoundEasy is invoked. The preferences are saved automatically on exit as well.

## 6. MLS System.

You can opt to use SPL/Phase calculated in MLS system directly as the driver transfer function. This way you'll by-pass HBT calculations – see Figure 1.4

🖪 System-Wide Preferences				
Frequency Range	Audio Devices	Environment		
System From: 2.0 Hz 🔺 To: 50000.0 Hz 🔺	🔲 Invert Data Channel	Temperature		
5.0 Hz 🔽 100000.0 Hz 🔽	Invert Reference Channel	Speed of Sound 344.00 m/s		
Box From: 2.0 Hz ▲ To: 50000.0 Hz ▲ 5.0 Hz ▼ 100000.0 Hz ▼	🗖 SE Controls Mixer 🛛 16 Bit Sound Card	Calibration 0.00 dB		
FEM From: 1.0 Hz  To: 500.0 Hz	Vou Control Mixer V 24 Bit Sound Card			
2.0 Hz 💌 1000.0 Hz 💌	□ Swap Card Inputs			
Graph Colour Scheme		CAD Labels Control ON/OFF		
Red • 68	Delay Output By [samples]	CAD Compare Labels		
Green $\checkmark$ $200$		SPL Colours		
	Preferred Input Waveform Device [out ot 8]			
Thickness 1 = 1 pixel A Type 1 = Solid	Line 1/2 (M-Audio Delta 1010LT), ID: 0	Cycle Colour		
2 = 2 pixels 2 = Dotted Thick / Type	Line 5/6 (M-Audio Delta 1010LT), ID: 2	CAD Nodes		
Dialogue Box Background	Monitor (M-Audio Delta 1010LT), ID: 3 🖃	☐ Automatic Node Numbering		
SPL Curve 2 1	Preferred Output Waveform Device [out of 11]			
Phase Curve 2 1	Line 1/2 (M-Audio Delta 1010LT), ID: 0	CAD Multiplots		
Impedance Curve 2 1	Realtek Digital Output(Optical), ID: 2	Automatic Multiplot		
🗆 Impedance Phase Curve 🔤 💶 1 1	Play 01+02 (Lyn× AES16-SRC), ID: 3 💽			
Group Delay Curve 2 1	Non-Linear Screen	FEM Node Limit 1350		
Cone Excursion Curve 2 1	Frequency Range	SPL Calculated In MLS		
Cone Velocity Curve 3 1	From: 1.0 Hz  To: 1000.0 Hz	Use It As Transfer Function		
Port/PR Excursion Curve     Port/PR Velocity Curve     1	2.0 Hz 2000.0 Hz	I Ose it as traiister Function		
✓ Port/PR SPL Curve 2 1	5.0 Hz 🔽 5000.0 Hz 🔽			
Enclosure Pressure Curve 1	Show F2,F3,F4 / F5,F6,F7 ESS Plots			
Power Demand Curve 1 1	Show THD Plots			
Back EMF Curve 21				
Phase Difference Curve 2 1	Scale: 0 - 100 %			
Time Domain FFT 2 1	0 - 1 %			
Time Domain MNM 1 1				
MLS In 1 1	CAD Screen Nodes			
MLS Ref 1 1	Show CAD Nodes			

Fig. 1.4 Example of Preferences screen settings

#### **User Interface Customization**

The GUI of the program has been designed around standard Windows<sup>™</sup> control-display techniques of using dialogue boxes to enter and control of the processing of the data and then using re-sizable windows to display the results. Typical control box is movable and has fixed size, and all plotting windows are re-sizable and movable. SoundEasy "remembers" the last location of the dialogue boxes and the size and location of the plotting windows, so perhaps the first step into the GUI should be the "customization" – meaning, moving around and adjusting the size of SoundEasy screens and dialogue boxes, depending on your PC screen size and resolution.

Minimum recommended screen size is: 1024x768 pixels. You can also use larger sizes: 1280x1024, 1600x1200pixels and so on.

As you may noticed already, the program is divided into several areas of functionality. For instance, when you concentrate on editing of the driver, it is unlikely, that you will need EasyLab screens opened at the same time. Therefore, SoundEasy automatically closes the EasyLab section when you work with the driver, enclosure, CAD or System sections of the program. This approach is applied consistently throughout the program and all unnecessary screens, that do not belong to the current activity are closed. However, be prepared, that many times, you will be working with 3 or 4 screens/control boxes opened at the same time.




Fig 1.5. Plotting window reduced in size




Fig 1.6 Plotting window maximized.

#### You can customize the look-and-feel of the GUI.

Please follow the main menu of the program and open menu items (screens) as you are moving from left-to-right along the menu. When you start the program for the first time, all windows will be opened with their respective default size and locations. Please feel free to make the necessary adjustments to suit your taste and your monitor. Next time you return to this screen, it will be opened in the same location and same size.

## **MLS Measurement Screen & Editor Screen**

In some instances, it may be beneficial to have uninterrupted access to Editor screen while you make measurements. This would allow you to setup measurement system once, perform an SPL or Zin measurement, save the driver file, open a new driver file obtain measurements for the new driver and save them an so on....

If you need to be working in this mode, please open the measurement screen first and then Driver Editor screen second. Both functions will stay opened now as shown for example on Fig 1.7.

#### **Driver & Project Notes**

It is often desirable to remember some unusual details about this particular driver file or a project file. Those details can now be conveniently entered into the **Notes Windows**. There are two Notes Windows: one associated with Driver File and one associated with Project File. Both Windows can store 1024 characters each.




Fig 1.7. MLS Measurement screen opened with Driver Editor screen.





Fig 1.8. Driver Notes window.

#### **Printing Driver and Project Data**

Apart from straightforward screen dump, there are three printing options for hard copy output.

- 1. Print Driver Selecting this option prints ALL parameters listed on Figure 1.9a,b, SPL/Phase curves and Zin/Phase curves. You may expect 2 pages of printouts.
- 2. Print Project Drivers Selecting this option prints ALL parameters listed on Figure 1.9a,b, SPL/Phase curves and Zin/Phase curves for ALL 5 drivers. You may expect 10 pages of printouts.
- 3. Print CAD + Parts List Selecting this option prints CAD schematic compressed to a single A4 page and complete parts list. You may expect the CAD schematic to be rather small. However, this is expected to providing printing capabilities for all home-type of printers with A4 capabilities.



#### Driver T/S Parameters

DC Resistance = 5.80 ohm Electrical Qe = 0.5405 Mechanical Qm = 5.46 Total Qt = 0.4918 VC Inductance = 0.31 mH Force Factor = 5.000 N/A Eddy Resistance = 39.00 ohm Compliance Volume = 1.3 Lt Nominal Power = 90.00 W Efficiency 1W/1m = 92.50 dB Piston Area = 50.265 cm<sup>2</sup> Effective Diameter = 8.0000 cm Max Linear Excursion = 2.50 mm Dynamic Mass = 2.000 gm Free Air Resonance = 185.395 Hz Dynamic Mass = 2.000 gm Accoustical Offset = 30.00 mm Magnetic Gap = 2.00 mm Voice Coil Height = 5.00 mm Thermal resistance VC-Magnet = 1.00 ohm Thermal resistance Magnet-Air = 0.280 ohm Thermal resistance Total = 1.28000 ohm VC Thermal Coefficient = 0.00393 mm Magnet Type = Alnico 5 Z min = 8.00 ohm Driver Type = Midrange Driver Model = AAA-85

#### Driver Volterra Parameters

Nonlinear\_BL0 = 4.9Nonlinear\_b1 = 82.0Nonlinear\_b2 = -20000.0Nonlinear\_K0 = 28.8Nonlinear\_k1 = -6067.0Nonlinear\_k2 = 9000000.0Nonlinear\_L0 = 0.0015Nonlinear\_l1 = 0.0873Nonlinear\_l2 = 10.0Nonlinear\_Rm = 2.6Nonlinear\_m = 0.014Nonlinear\_Eg = 17.0

#### Non-Linear Diff-EQ Parameters

Asymmetry BL (A1) = 0.00000 Flat/Peak BL (A2) = -0.02000 Wide/Narrow BL (A4) = -0.00500 Shift BL (AS) = 0.00000 Asymmetry Cas (B1) = 0.000000 Flat/Peak Cas (B2) = -0.00022 Wide/Narrow Cas (B4) = -0.00150 Shift Cas (BS) = 0.00000

Figure 1.9b. T/S parameters printout example.

#### **Driver Characteristics Screen**

At times, it may be convenient to have detailed information about individual drivers in the project available at your fingertips. You and o just that, by selecting any of the driver file from: "Enclosure Design" -> "Show Driver XXXXX File" menu option.

A screen similar to the one shown below will be opened, where you can examine **amplitude** + **phase transfer function**, **input impedance** + **phase transfer function** and also all related mechanical and TS parameters.

Please note, that transfer functions that are displayed in this window, are used by the remainder of the program. So, this gives you a good opportunity to instantly examine, if your HBT generated transfer functions were correct. You should be able to open HBT dialogue box, change the HBT parameters, plot the new transfer function, and then open the Driver Characteristics window to examine the newly created changes to the transfer functions.

The Driver Characteristics window will also display file names and directory paths for all 5 possible drivers in your project. You may find this information quite handy, and be able to access it from anywhere throughout the program.





Figure 1.10. Example of Driver Characteristics window opened for woofer driver.

#### **Help Files On-Line**

There are several Help Files incorporated in this release. These files are accessible via a "Help" button where applicable. An example of a Help File related to CAD system is shown below.



The most recommended help file has been written by John Kreskovsy. This file can be accesses via "User Help" -> "SoundEasy Help" menu option. Information contained in this file will help you navigate through SoundEasy and also will provide you with general assistance with building your loudspeakers – highly recommended !.

## **Dongle Serial Number**

Your electronic key ( dongle ) serial number is displayed in the "About" dialogue box – see below – ABCD23456.



Figure 1.12. ABCD23456 serial number in "About" dialogue box.